GstarCAD server license OPT configuration file

1192 kbadmin November 23, 2021 Activate / Deactivate 0 8756

The options file allows the license administrator to control various operating parameters of FLEXIm. Specifically the license administrator can:

- Allow the use of features based on user, hostname, or display name.
- Deny the use of features based on user, hostname, or display name.
- Reserve licenses based on user, hostname, or display name.
- Control the amount of information logged about license usage.

Options files allow you, as the license administrator, to be as secure or open with licenses as you like.


Lines in the options file were limited to 200 characters prior to FLEXIm v3.0. In v3.0 and later, the line length is 2048 characters. FLEXIm v4.0 allows the `character as a continuation character in options file lines.

To create an options file

• Use the appropriate options to create the options file using any text editor. You can put the options file anywhere; however, we recommend that the option file for vendor GstarCAD be placed in


LMTOOLS 11.14 (2019 version or older) C:Program FileGstarCAD NetWork License Managergstarlms.opt

Network License Manager (2020 version or latest) C:Program FilesCommon FilesGstarsoftLicense servicegstarlms.opt



2. Add the pathname to the options file in the license file. The fourth field on the DAEMON line for the application's vendor daemon.

For example,



would enable the gstarlms vendor daemon to look at the specified options file.

Ignore if step use default license file at Network License Manager (2020 version or latest)

Rules of Precedence in Options Files

Before you can use options to utilize licenses effectively you must understand the options file precedence. INCLUDE and EXCLUDE statements can be combined in the same options file and control access to the same features. When doing so, keep in mind the following:

- If there is only an EXCLUDE list, everyone who is not on the list will be allowed to use the feature.
- If there is only an INCLUDE list, only those users on the list will be allowed to use the feature.
- If neither list exists, then everyone is allowed to use the feature.
- The EXCLUDE list is checked before the INCLUDE list; so someone who is on both lists will not be allowed to use the feature.

Once you create an INCLUDE or EXCLUDE list everyone else is implicitly 'outside' the group. This feature allows you, as an administrator, the ability to control licenses without having to explicitly list each user that you wish to allow or deny access to. In other words there are two approaches; you can either:

- Give most users access and list only the exceptions or
- Severely limit access and list only the those users that have access privileges.

GROUP groupname usernamelist

Defines a group of users for use in INCLUDE, INCLUDEALL, EXCLUDE, EXCLUDEALL, and RESERVE option lines.

groupname - name of the group being defined usernamelist - list of user names in that group

To define the group ENGINEERING consisting of A1, A2, A3 and A4, and the group SALES consisting of B1, B2 and B3 (*Where An and Bn is user name*)

GROUP ENGINEERING A1 A2 A3 A4 A5 GROUP SALES B1 B2 B3

In FLEXIm v3.0 multiple GROUP lines will add all the users specified into the group. Pre-v3.0 FLEXIm daemons do not allow multiple GROUP lines to concatenate. In fact, the second GROUP line would redefine the GROUP.

In FLEXIm v4.0 or later, USER_GROUP is an alias for GROUP...

HOST_GROUP *groupname hostnamelist*

Defines a group of hosts for use in INCLUDE, INCLUDEALL, EXCLUDE, EXCLUDEALL, and

RESERVE option lines.

- groupname name of the group being defined
- hostnamelist list of host names in that group

To define the group TECHNICAL consisting of tech1, tech2, and tech3: (*where tech<u>n</u> is host or PC name*)

GROUP TECHNICAL tech1 tech2 tech3

INCLUDE *featurename type name*

Includes a user, host, display, or group in the list of who is allowed to use the feature. Anyone not in an INCLUDE statement will not be allowed to use that feature.

- featurename name of the feature being affected
- type one of USER, HOST, DISPLAY, GROUP, or HOST_GROUP
- name name of the user or group to include

HOST_GROUP is available for FLEXIm v4.0 and later.

To include user `A1' in the list of users able to use feature GSCAD2_2011, where GSCAD2_2011 is GstarCAD Standard and GSCAD1_2011 is GstarCAD Professional:

INCLUDE GSCAD2_2011 USER A1

INCLUDE GSCAD2_2011 HOST tech1

INCLUDE GSC	AD2_2011	GROUP SALES			
INCLUDE GSC	'AD2_2011	HOST_GROUP	TECHNICAL		

where:

- GSCAD2_2011 is the GstarCAD Professional
- GSCAD1_2011 is the GstarCAD Standard
- GSCAD5_2011 is the GstarCAD LT
- GSCAD10_2011 is the GstarCAD Education

and _2011 are all available released, NOT definite as GstarCAD2011

Simple Options File Example

Limiting Access for Multiple Users by Group

GROUP ENGINEERING A1 A2 A3 A4 A5 GROUP SALES B1 B2 B3

INCLUDE GSCAD1_2011 GROUP ENGINEERING
INCLUDE GSCAD1_2011_ENG GROUP ENGINEERING

INCLUDE GSCAD2_2011 GROUP SALES INCLUDE GSCAD2_2011_ENG GROUP SALES

Limiting Access for Multiple Users by ip address

INCLUDE GSCAD1_2011 INTERNET 192.168.0.98
INCLUDE GSCAD1_2011_ENG INTERNET 192.168.0.98

INCLUDE GSCAD2_2011 INTERNET 192.168.0.92
INCLUDE GSCAD2_2011_ENG INTERNET 192.168.0.92

Prevents any user logged into a host with an IP address in the range 192.168.11.0 through 192.168.11.255 from using the feature "GSCAD1 2011."

EXCLUDE GSCAD1_2011 INTERNET 192.168.11.*

EXCLUDE GSC.	AD1_2011_EN	G INTERNET 1	192.168.11.*		

Limiting Access for Multiple Users by IP address with version control

192.168.0.98 allow to use GstarCAD 2015 PRO and blocked to use 2016 version

EXCLUDE GSCAD1_2011:VERSION=2016 INTERNET 192.168.0.98
EXCLUDE GSCAD1_2011_ENG:VERSION=2016 INTERNET 192.168.0.98

INCLUDE GSCAD1_2011:VERSION=2015 INTERNET 192.168.0.98
INCLUDE GSCAD1_2011_ENG:VERSION=2015 INTERNET 192.168.0.98

EXCLUDE GSCAD1_2011:VERSION=2015 INTERNET 192.168.0.92 EXCLUDE GSCAD1_2011_ENG:VERSION=2015 INTERNET 192.168.0.92

INCLUDE GSCAD1_2011:VERSION=2016 INTERNET 192.168.0.92
INCLUDE GSCAD1 2011 ENG:VERSION=2016 INTERNET 192.168.0.92

where VERSION=2016 is GstarCAD 2016

Online URL: https://www.kb2.gstarcad.com.my/article.php?id=1192