

Parameters — GstarCAD 2027

4473 kbadmin September 25, 2026 [User Guide](#) 0 8

Parameters

[GstarCAD 2027](#) · [User Guide](#)

User Guide > Create and Modify Objects > Create and Use Blocks > Dynamic Blocks > Parameters

Define custom properties for the dynamic block by specifying positions, distances and angles for geometry in the block.

You add parameters to a dynamic block definition in the Block Editor. In the Block Editor, parameters have an appearance similar to dimensions. Parameters define custom properties for the block. Parameters also specify positions, distances, and angles for geometry in the block reference. When you add a parameter to a dynamic block definition, the parameter defines one or more custom properties for the block.

A dynamic block definition must contain at least one parameter. When a parameter is added to a dynamic block definition, grips associated with key points of the parameter are automatically added. You must then add an action to the block definition and associate the action with a parameter.

Parameters also define and constrain values that affect the dynamic block reference's behavior in a drawing. Some parameters can have a fixed set of values, minimum and maximum values, or increment values. For example, a linear parameter used in a window block may have the following fixed set of values: 10, 20, 30, and 40. When the block reference is inserted in a drawing, you can only change the window to one of these values. Adding a value set to a parameter allows you to limit how the block reference is manipulated in a drawing.

Point Parameter

Command Line: BPARAMETER > O

Defines an *X* and *Y* location in the drawing. A point parameter can be associated with a move or stretch action.

Icon:

Linear Parameter

Command Line: BPARAMETER > L

Shows the distance between two anchor points. Constrains grip movement along a preset angle. A linear parameter can be associated with a move, stretch, scale or array action.

Polar Parameter

Command Line: BPARAMETER > P

Shows the distance between two anchor points and displays an angle value. You can use both grips and the Properties palette to change both the distance value and the angle. A polar parameter can be associated with a move, scale, stretch, polar stretch, or array action.

Icon:

XY Parameter

Command Line: BPARAMETER > X

Shows the *X* and *Y* distances from the base point of the parameter. It can be associated with a move, scale, stretch, or array action.

Rotation Parameter

Icon:

Command Line: BPARAMETER > R

Defines an angle. The rotation angle can be in any value, or be defined in a range or a specified value.

Alignment Parameter

Command Line: BPARAMETER > A

Defines an X and Y location and an angle. An alignment parameter always applies to the entire block and needs no action associated with it. An alignment parameter allows the block reference to automatically rotate around a point to align with another object in the drawing. An alignment parameter affects the rotation property of the block reference.

Flip Parameter

Command Line: BPARAMETER > F

A flip parameter flips objects. You can associate a flip parameter with a flip action.

Visibility Parameter

Command Line: BPARAMETER > V

Controls the visibility of objects in the block. A visibility parameter always applies to the entire block and needs no action associated with it. In a drawing, you click the grip to display a list of visibility states available for the block reference.

Lookup Parameter

Command Line: BPARAMETER > K

Icon:

Defines a custom property that you can specify or set to evaluate a value from a list or table you define. It can be associated with a single lookup grip. In the block reference, you click the grip to display a list of available values. You can associate a lookup parameter with a lookup action.

Base Point Parameter

Command Line: BPARAMETER > B

Defines a base point for the dynamic block reference relative to the geometry in the block. Can not be associated with any actions, but can belong to an action's selection set.

Other versions with matching text

[2022](#) · [2023](#) · [2024](#) · [2025](#) · [2026](#)

Online URL: <https://www.kb2.gstarcad.com.my/article.php?id=4473>

Icon: