

Attach DWF Underlay Dialog Box — GstarCAD 2027

4316 kbadmin September 25, 2026 [Command Reference](#) 0 9

Attach DWF Underlay Dialog Box

[GstarCAD 2027](#) · [Command Reference](#)

Commands > D Command > DWFATTACH > Attach DWF Underlay Dialog Box

Function Description:

Sets options such as rotation and scale when you attach a DWF underlay. Names, locates and defines the insertion point, scale and rotation of attached DWF or DWFx underlays.

Dialog Box Options:

Name

Identifies the DWF or DWFx file you have selected to attach.

Browse

Opens the Select Reference File dialog box.

Select one or more sheets from DWF file

Displays all of the sheets that are found in the DWF file. If the DWF file only contains a single sheet, that sheet is listed. You can select multiple sheets by holding the Shift key or the Ctrl key while selecting the sheets to attach. If you hover over the preview, the file name displays.

Path Type

Selects the Full path, Relative path and No path to the DWF file. The default path type is Relative path.

Insertion Point

Specifies the insertion point for the selected DWF file. Specify On-screen is the default. The default insertion point is 0,0,0.

- Specify On-screen: Directs input at the Command prompt or the pointing device. If Specify On-screen is cleared, enter the insertion point in X,Y and Z.
- X: Sets the X coordinate value.
- Y: Sets the Y coordinate value.
- Z: Sets the Z coordinate value.

Scale

Specifies the scale factor of the selected DWF underlay.

- Specify On-screen: Allows you to input at the Command prompt or the pointing device. If Specify On-screen is cleared, enter a value for the scale factor. The default scale factor is 1.
- Scale Factor Field: Enters a value for the scale factor. The default scale factor is 1.

Rotation

Specifies the rotation angle of the selected DWF underlay.

- Specify On-screen: If Specify On-screen is selected, you may wait until you exit the dialog box to rotate the object with your pointing device or enter a rotation angle value at the Command prompt.

- Angle: If Specify On-screen is cleared, enter the rotation angle value in the dialog box. The default rotation angle is 0.

Show Details/Hide Details

Displays the DWF file path.

- Location: Displays the path where the DWF file is located.
- Saved Path: Displays the path that is saved with the drawing when the DWF file is attached. The path is dependent upon the Path Type setting.

Other versions with matching text

[2022](#) · [2023](#) · [2024](#) · [2025](#) · [2026](#)

Online URL: <https://www.kb2.gstarcad.com.my/article.php?id=4316>