

MLEADER Command — GstarCAD 2027

3632 kbadmin September 25, 2026 [Command Reference](#) 0 19

MLEADER Command

[GstarCAD 2027](#) · [Command Reference](#)

Commands > M Command > MLEADER

Function Description:

This command is used to create an object with a multileader.

The multileader object usually contains of an arrowhead, a horizontal baseline, a leader line or curve and either a multiline text object or a block.

The multileaders can be created arrowhead first, leader landing first or content first.

If a multileader style has been used, users can create a new multileader based on the specified style.

Command Access:

Menu: Dimension > Multileader

Ribbon: Annotation > Leader > Multileader

Toolbar: Multileader > Multileader

Command: MLEADER

Alias: MLD

Command Prompts:

Specify leader arrowhead

location or [leader Landing first/Content first/Options] <Options>:

Leader arrowhead location

Specifies the location for the arrowhead of a multileader.

- **Specify leader landing location:**

Specify the leader landing location of a multileader.

If exiting the command at this step, it will not create text associated with a multileader.

Leader landing first

Specifies the leader landing location of a multileader.

- **Specify leader arrowhead location:**

Specify the location of arrowhead of a multileader.

If exiting the command at this step, it will not create text associated with a multileader.

Content first

Specifies the location for the text or block that associated with a multileader.

- **Specify first corner of text:**

Specify the text box by two corner points. This text box defines the location of text label that associated with a multileader. After inputting text, click "OK" or click a point outside of text box to finish.

Options

Specifies options for placing a multileader.

- **Leader type:**

Specifies how the leader line is handled, the leader type can be straight line, spline or no leader.

- **Leader lAnding:**

Specifies whether to add a horizontal landing line. Users can choose Yes option to

set the landing line length or No option to create a multileader without a leader landing.

-

Content type:

Specifies the content type that will be used for the multileader.

-

Block: Specifies a block to associate with the new multileader.

- **Mtext:**

Specifies a multiline text to be contained in a multileader.

-

None:

Specifies that no content is displayed at the end of the leader line.

-

Maxpoints:

Specifies a max number of points for the new multileader.

- **First angle:**

Specifies the first angle for the new multileader.

- **Second angle:**

Specifies the second angle for the new multileader.

Related References[?]

- [Commands about Creating Leaders](#)

Related Tasks[?]

- [To Create a Leader With Lines](#)
- [To Create a Spline Leader With Text or a Block](#)
- [To Create Multiple Leaders From the Same Annotation](#)

Other versions with matching text

[2023](#) · [2024](#) · [2025](#) · [2026](#)

Online URL: <https://www.kb2.gstarcad.com.my/article.php?id=3632>