

SALPL — GstarCAD 2027

5904 kbadmin September 26, 2026 [Command Reference](#) 0 9

SALPL

[GstarCAD 2027](#) · [Command Reference](#)

Using this function can easily draw an axonometric drawing.

Operation Steps:

1.Start the command.

2.Input the line width value.

3.The command line will prompt as below, input corresponding options, you can use it to switch between 0 degree and 45 degree and you can also input any angle value.

4.Enter to finish the command.

Other versions with matching text

[2025](#) · [2026](#)

Online URL: <https://www.kb2.gstarcad.com.my/article.php?id=5904>